

ØMQ for OpenVMS I64 and Alpha

Brett Cameron (brett.cameron@hp.com), John Apps (john.apps@hp.com) March 2011

Disclaimer: the information in this document is the sole responsibility of the authors. The information contained herein is offered on a best-effort basis. Hewlett-Packard offers no support or warranty on any of the content in this document or the software described in it.

1. Introduction

Thank you for your interest in this port of ØMQ (ZeroMQ) to OpenVMS. The current release of ØMQ for OpenVMS is based on the ØMQ 2.1.2 distribution.

ØMQ (<http://www.zeromq.org>) is a messaging system that aims to address many of the problems of more traditional enterprise messaging solutions such as complexity and bloat. ØMQ tackles these issues by taking a different approach. Instead of inventing new APIs and complex wire protocols, ØMQ extends the socket API, eliminating the learning curve and allowing a network programmer to master it in just a few of hours.

The wire protocols employed by ØMQ are deliberately simplistic, even trivial, and performance of ØMQ matches and often exceeds that of raw sockets. Speeds of over 8 million messages per second with a latency of some 12µs have been measured using standard Intel hardware and Linux together with Infiniband. Less spectacular results will be obtained with standard OpenVMS configurations; however good performance combined with the simplicity of the ØMQ programming model make the software an excellent option for the development of any TCP/IP sockets-based application.

This OpenVMS port of ØMQ includes almost all ØMQ. The port presently does not provide support for reliable multicast (via OpenPGM) and does not support direct (non-TCP/IP) inter-process communication. It is anticipated that these deficiencies will be addressed in future releases.

2. Acknowledgements

The authors would like to acknowledge the support and assistance of the ØMQ team in the creation of this release. We would also like to thank Brian Reiter for providing the Pascal examples.

3. What's new in this release

For a detailed description of the new features and bug fixes included in this release, please read <https://github.com/zeromq/zeromq2-1/raw/master/NEWS>.

4. Requirements

The kit you are receiving has been compiled and built using the operating system and compiler versions listed below. While it is highly likely that you will have no problems installing and using the kit on systems running higher product versions of the products listed, we cannot say for sure that you will be so lucky if your system is running older versions. If you require a kit for a different configuration, we will do what we can to oblige. Note that the UnZip utility is required in order to unpack the ZIP kit.

- OpenVMS 8.3 (I64 or Alpha) or higher
- HP TCP/IP Services V5.6 or higher

It has not been verified whether the kit works with the MultiNet TCP/IP stack, but there is a good chance that it will.

- C compiler - HP C V7.1-015 or higher
- C++ compiler - HP C++ V7.3-009 or higher

Note that the C++ is required in order to build ØMQ applications. Specifically, the CXXLINK utility must be used on OpenVMS Alpha in order to link applications; on OpenVMS Integrity, the standard LINK command may be used.

- UnZip 5.42 (or similar) for OpenVMS (required to unpack the ZIP kit and can be found on the OpenVMS Freeware CD)

In addition to the above requirements, it is assumed that the reader has a good knowledge of OpenVMS and of software development in the OpenVMS environment.

5. Recommended reading

Before getting too carried away, be sure to read (or at least browse) the very comprehensive documentation on the ØMQ web site (<http://www.zeromq.org>). In addition to programming guides, there are whitepapers and assorted other documents that provide plenty of useful information on how ØMQ can be used.

6. Contents of the kit

The kit is currently provided as a ZIP file (created using Zip 2.3 for OpenVMS), which allows individual users to install the software under their own accounts, if so desired.

The following file listing represents the output from the `unzip -l` command run against the ZIP file kit on OpenVMS I64 (the listing on OpenVMS Alpha would be very similar).

```
Archive:  DISK$USER:[BIGGLES]ZEROMQ-212-VMS-I64.ZIP;1
 Length   Date    Time    Name
-----
      0   05-10-10  21:05   zmq/bin/
    9603   02-23-11  22:48   zmq/copying.lesser
   35149   03-07-11  14:29   zmq/copying.txt
      0   05-10-10  21:05   zmq/doc/
      0   05-10-10  21:05   zmq/examples/
      0   05-10-10  21:05   zmq/include/
      0   05-10-10  21:05   zmq/lib/
     535   12-17-10  08:57   zmq/zmq$startup.com
  1242112  03-07-11  14:28   zmq/bin/zmq$shr.exe
  146432   03-07-11  14:29   zmq/bin/zmq_forwarder.exe
  145920   03-07-11  14:29   zmq/bin/zmq_queue.exe
  145920   03-07-11  14:29   zmq/bin/zmq_streamer.exe
   23108   02-23-11  22:59   zmq/doc/zmq.html
   17102   02-23-11  22:59   zmq/doc/zmq_bind.html
   14676   02-23-11  22:59   zmq/doc/zmq_close.html
   17079   02-23-11  22:59   zmq/doc/zmq_connect.html
   22453   02-23-11  22:59   zmq/doc/zmq_cpp.html
   19830   02-23-11  22:59   zmq/doc/zmq_epgm.html
   14330   02-23-11  22:59   zmq/doc/zmq_errno.html
   13243   02-23-11  22:59   zmq/doc/zmq_forwarder.html
   40886   03-06-11  22:23   zmq/doc/zmq_getsockopt.html
   14308   03-06-11  22:23   zmq/doc/zmq_init.html
   16249   02-23-11  22:59   zmq/doc/zmq_inproc.html
   15832   02-23-11  22:59   zmq/doc/zmq_ipc.html
   14633   02-23-11  22:59   zmq/doc/zmq_msg_close.html
   14926   02-23-11  22:59   zmq/doc/zmq_msg_copy.html
   14145   02-23-11  22:59   zmq/doc/zmq_msg_data.html
   14965   02-23-11  22:59   zmq/doc/zmq_msg_init.html
   15692   02-23-11  22:59   zmq/doc/zmq_msg_init_data.html
   15034   02-23-11  22:59   zmq/doc/zmq_msg_init_size.html
   14532   02-23-11  22:59   zmq/doc/zmq_msg_move.html
   14157   02-23-11  22:59   zmq/doc/zmq_msg_size.html
   19830   02-23-11  22:59   zmq/doc/zmq_pgm.html
   19294   02-23-11  22:59   zmq/doc/zmq_poll.html
   13227   02-23-11  22:59   zmq/doc/zmq_queue.html
   17856   02-23-11  22:59   zmq/doc/zmq_recv.html
   17959   03-06-11  22:23   zmq/doc/zmq_send.html
   38617   03-06-11  22:23   zmq/doc/zmq_setsockopt.html
   34651   03-06-11  22:23   zmq/doc/zmq_socket.html
   13242   02-23-11  22:59   zmq/doc/zmq_streamer.html
   14224   02-23-11  22:59   zmq/doc/zmq_strerror.html
   19999   02-23-11  22:59   zmq/doc/zmq_tcp.html
   15261   03-06-11  22:23   zmq/doc/zmq_term.html
   14253   02-23-11  22:59   zmq/doc/zmq_version.html
```

```

1958 03-05-11 17:03 zmq/examples/build.com
3549 03-07-11 12:14 zmq/examples/cob_remote_lat.cob
1589 06-11-10 22:11 zmq/examples/f_local_lat.for
 660 03-05-11 19:02 zmq/examples/mt-client.cpp
2030 03-05-11 19:12 zmq/examples/mt-server.cpp
2770 01-10-11 11:36 zmq/examples/p_local_lat.pas
3157 01-10-11 11:36 zmq/examples/p_remote_lat.pas
3451 03-07-11 14:21 zmq/examples/zmq.pas
4404 03-07-11 14:19 zmq/include/zmq.cpy
9344 03-05-11 23:25 zmq/include/zmq.h
7010 03-05-11 23:25 zmq/include/zmq.hpp
5306 03-07-11 14:17 zmq/include/zmq.inc
2928640 03-07-11 14:28 zmq/lib/libzmq.olb
-----
5285132                               57 files

```

6.1. Installing the kit

Unpacking and installing the ZIP file kit is very straightforward. After copying the supplied ZIP file (ZEROMQ-212-VMS-AXP.ZIP for OpenVMS Alpha or ZEROMQ-212-VMS-I64.ZIP for OpenVMS I64) to a suitable location, unpack the contents of the relevant ZIP file using the unzip command.

For example, for the Alpha kit, you would enter the following command:

```
$ unzip ZEROMQ-212-VMS-AXP.ZIP
```

After unpacking the kit, you will have a [.zmq] directory below your current directory that contains files listed above. Note that you can install the software onto either an ODS2 or an ODS5-formatted disk.

6.1.1. Post-installation steps

To complete the installation it is necessary to define the concealed logical name ZMQ\$ROOT to point to your top-level [.zmq] directory and to define a logical name for the shareable image ZMQ\$SHR.EXE. You may optionally wish to install the shareable image.

A sample command procedure called ZMQ\$STARTUP.COM that illustrates these logical name definitions and installation of the shareable image is provided in the top level [.zmq] directory (see listing below). You may wish to modify this file as required and include it in your system start-up procedure.

```

$ ! ZMQ$STARTUP.COM
$ !+
$ ! 17-Dec-2010
$ ! Startup file for ZeroMQ 2.1.0 on OpenVMS
$ !-
$
$ set noon
$ !
$ if f$trnlm("zmq$root","lnm$system_table",,,,).eqs. ""
$ then
$   ! Modify definition for zmq$root as appropriate
$   !
$   define/sys/exec/tran=(conc,term) zmq$root dorone$dka0:[zmq.]
$ endif
$
$
$ write sys$output "ZMQ-I-INSTALL, Installing ZMQ$SHR"
$ define/sys/exec zmq$shr zmq$root:[bin]zmq$shr.exe
$ install replace zmq$shr/header_resident/open/shared
$
$ write sys$output "ZMQ-I-DONE, Startup complete"
$ !
$ exit

```

Note that in the above example the ZMQ\$ROOT logical name is defined in the system table. It is possible to define the logical name at a lower level (such as GROUP level) in order that multiple users may run ØMQ in their own process space.

6.2. Privileges and quotas

Generally speaking there are no special quota or privilege requirements for applications developed using ØMQ, although a high BYTLM is recommended, and SYSPRV, BYPASS, or OPER privilege will be required if ØMQ processes need to utilise privileged ports (ports below 1024).

The authors typically operate (on OpenVMS IA64) with quota settings similar to the following, which should be more than adequate for most purposes:

Maxjobs:	0	Fillm:	256	Bytlm:	128000
Maxacctjobs:	0	Shrfillm:	0	Pbytlim:	0
Maxdetach:	0	BIOLm:	150	JTquota:	4096
Prclm:	50	DIOLm:	150	WSdef:	4096
Prio:	4	ASTlm:	300	WSquo:	8192
Queprio:	4	TQElm:	100	WSextent:	16384
CPU:	(none)	Enqlm:	4000	Pgflquo:	256000

7. Sample applications

The `zmq$root:[samples]` directory contains two simple examples that can be used to measure latency¹ and throughput. These examples can be compiled and linked using the provided build procedure (`build.com`). Once built, these programs are simple to run. For example, for the latency example, to measure the latency for a 16-bytes message using a sample size of 10000 messages, on one machine we could run the following command:

```
$ mcr []local_lat.exe "tcp://16.156.32.107:5555" 16 10000
```

And on another machine we would enter the following command:

```
$ mcr []remote_lat.exe "tcp://16.156.32.107:5555" 16 10000
```

When the run completes, `remote_lat.exe` will display the results as follows (the latency will vary, depending on your specific hardware, operating system, and network configuration):

```
message size: 16 [B]
roundtrip count: 10000
average latency: 263.000 [us]
```

In addition to these examples, additional example code may be found on the ØMQ web site. For example, see <http://www.zeromq.org/docs:cookbook>.

8. What's missing?

As noted previously, the bulk of the ØMQ functionality is present, and it should be possible to do much of what is described on the ØMQ web site. Support for reliable multicast (via OpenPGM) is not currently supported, nor is non-TCP/IP IPC.

Under UNIX/Linux, ØMQ leverages UNIX sockets to provide an efficient non-TCP/IP IPC mechanism; however such facilities are not available on OpenVMS and the authors are considering various other options.

ØMQ also supports a range of language bindings, including scripting languages such as Ruby and Lua, and 3GL languages such as Ada. The authors are working to provide similar options on OpenVMS, including a version of the ØMQ API that can be readily called from any OpenVMS 3GL, such as COBOL, FORTRAN, and so on (much of this work has in fact been completed; however further testing, documentation, and creation of examples is required before the API can be made available).

¹ Latencies on the order of 200µs on an rx2620 have been achieved on OpenVMS Integrity. Latencies on OpenVMS Alpha may be 4 or 5 times greater, depending on the age and configuration of the hardware and software in question.

Appendix

Tools

Over time the authors will update this document with tools they have found useful in the course of their work. The authors welcome any suggestions and will include them in future versions of the document.

- Zip and UnZip for OpenVMS may be obtained from the OpenVMS freeware CD at <http://h71000.www7.hp.com/openvms/freeware/>.